

Stret Fasin blong Planem Sandalwud

1. Stret spacing blong planem
Sandalwud emi 4m x 4m. Yu
save planem wetem kakai mo
wetem ol narafala peminan host tri
olsem aranis, Kasis, Nangai mo
Namariu.



2. Sandalwud I kro gud long kraon
we I drae.
3. Stret taem blong Sandalwud tri gat
natora blong hemi 20-30 yia.
4. Sandalwud I nidim pruning (katemaot ol
fes branj we I kro daon) taim I gat 3 yia
olsem . Mekem tinning (katemaot sam
spos ol wud I fasfas tumas).

Faenol prodak

- 1.Yu save mekem mani long sids, rus,
stampa, mo branj..




**Sapos yu wantem moa infomesen
long Sandalwud**

**Kontaktem Dipatmen blong
Forestri long Vila
or luk ol Forest Ofisa long Provins
blong oli save helpem yu.**

**Address blong mifala I stap andanit
long pepa ia wetem telephone namba
blong Dipatmen.**

**Forest Department
PMB 9064
Port Vila**

**Phone: 23171/23856
Fax: 23856
E-mail: forestry@yahoo.com.vu**



**Stret Fasin
blong Planem
Sandalwud**

**Dipatmen blong Forestri I prodiusum
smol liflet ia wetem faenensial sapot
blong NZaid long saed blong wudlot
trening mo neseri manejmen**

Stret taem blong Sandalwud frut I redi



Frut blong sandalwud I redi long manis blong January, May, June mo July mo bageken long manis Novemba mo Disemba long evri yia.

Hao blong jekem se frut I redi?

1. Jekem se frut I redi mo I black gud.
2. Samtaem ol sids we oli foldaon daon long kraon oli no gud be mek sua se sapos yu kolektem hemia we I foldaon long graon hemia we oli fres nomo.
3. Pikimap ol sids kwik taem from samtaem pijin I save kakai mo dropem long narafala ples mo taim oli foldaon, rat tu I save kakai olgeta.

Hao nao bai blong tritim ol sids afta we oli kolektem



1. Fulumap long wan klin bak mo livim I stap kasem taim skin I sting. Afta we skin I sting yu washemaot ol skin ia mo putum ol sids long wan klin kalico blong I drae.
2. Mas fulumap ol sids long wan bak blong mekem se rat ino kakai.
3. Livim I stap bak blong 1 o 2 manis bifo planem long jeminesen bokis.
4. Testem ol sids fastaem. Blong testem, fulumap wota long wan baket o dish afta putum ol sids iko mo livim I stap ova naet. Olgeta we oli flot yu karemaot mo sakem. Olgeta we oli draon, planem long jeminesen bokis mo kavremap gud long wan plastic bak or krin net afta livim andanit long wan smol shelta.

Stret Fasin blong lukaotem ol sidlings long neseri



1. Yu mas mixim kraon blong yu. Yu karem 2 bag kraon mo wan bag sandbis mo mixim gud biffo yu fulumap long germination box blong yu. Mo mekem sem samting long kraon insaed long ol plastic blong yu.
2. Yu mas wotarem ol sids ia blong mekem se kraon I Wetwet oltaem.
3. Afta 2-3 wiiks ol sids I stat blong gro mo yu mas karemaot bag coprah blong mekem se ol sids I fri blong gro stret igo antap.
4. Taem we oli gro mo gat 2-3 lifs yu karemaot olgeta mo planem insaed long ol plastic blong yu long standout bed wetem **Anternedra** we hemi host plant blong hem. Pulumaot eni kras we I gro insaed long plastic blong blokem competisen long kakai.
5. Bambae oli stap long stand out bed blong narafala 3 manis afta yu karemaot lif coconut or krin net blong yu mo lego I stap long sun blong narafala 3 manis biffo yu save planemaot long fil.